


Color Separations Flexographic Plates 3M Distributor

Cheat Sheet Topic: Using the WebCenter Viewer


Purpose: To outline the tools available in the WebCenter Viewer.

Applications Needed: Internet Browser [with Java]

- 1. There are a handful of different ways to open a document in the viewer:
 - a. From anywhere in WebCenter, click the document's thumbnail.



b. From the Document Details page, click View and Annotate under Document Actions.



c. From the project folder, check the box next to a document, go to the action button, and choose View and Annotate.



2. In the viewer, you have several tools available to help you inspect areas of the document.

(Continued next page...)



- 1. Document information
- 2. Document display window
- 3. Viewer functions:



4. Basic tools:

Zoom tool: Click anywhere in the document window to zoom in

Click + drag around an area of the document you wish to zoom in on

Ctrl + click in the document window to zoom out

Double-click on the zoom tool to fit document in window

Hand tool: Click + drag in the document window to pan to different areas of the document

Ruler tool: Click two points in the document window for point-to-point distance measurement

(May be used in conjunction with the zoom tool for precise measurement)

Densitometer: Click in an area of the art to measure the ink percentages in that area

5. Navigator: Drag the red box to view different areas of the art at the same zoom level 6. View tools: Cycle backward and forward through the last views of the document Rotates the document clockwise in 90-degree increments Mirror: Mirrors the document 7. Channels: Each color in the document listed with swatch and name Click on any color swatch to change its display color Toggle a color on or off View a single color in black 8. Annotations: Marquee: Click + drag around an area of the document you wish to comment on Click on a single point of the document you wish to comment on X Delete: Deletes the currently highlighted annotation (Note: you will not be able to delete annotations made by other users)

9. Size information: Page size and view resolution of the current document

Commit: Saves your annotations